



ALPHABOX CLOUD — ENTERPRISE DEPLOYMENT PROTOCOL

Please follow these instructions sequentially to initialize your terminal and authenticate with the AlphaBox routing engine.

1. SYSTEM INSTALLATION

Deploy the executable file into the MetaTrader 5 root directory.

- Launch MetaTrader 5 and navigate to **File** → **Open Data Folder** .
- Access the **MT5\Experts** directory.
- Deposit the **AlphaBox Cloud.ex5** file into this location.

2. TERMINAL CONFIGURATION

Network and execution permissions must be granted to the terminal engine.

- Navigate to **Tools** → **Options** → **Experts** .
- Enable **Allow algorithmic trading** .
- Enable **Allow WebRequest for listed URL** .

CRITICAL REQUIREMENT: You must allow the AlphaBox node addresses to the WebRequest URL list:

Enter the **Main Cloud Address** and the **Backup Cloud Address** that you received in your email (e.g., **1.12.123.11**).

Once allowed, click **OK** .

- Restart the MetaTrader 5 terminal to apply the new system configurations.



3. CHART DEPLOYMENT

Attach AlphaBox Cloud.ex5 to an active market chart to authenticate your license key.

- Open an active chart for **XAU/USD**. (Note: The engine automatically maps broker-specific instrument suffixes, e.g., XAUUSD+, XAUUSD.p, XAUUSDm or GOLD).
- Select any preferred timeframe.
- From the Navigator panel, execute **AlphaBox Cloud** onto the chart.

4. AUTHENTICATION & PARAMETERS

- Under the **Common** tab, verify **Allow Algo Trading** is enabled.
- Under the **Inputs** tab, enter your unique **AlphaBox License Key** that you received on your email.
- In the **Main Cloud Address** field, enter the Main Cloud address that you received on the email.
- In the **Backup Cloud Address** field, enter the Backup Cloud address that you received on the email.
- **Mobile push on network drops** : Enable this to receive mobile push notifications if the AlphaBox Cloud network connection drops.
- **Equity allocation per trade** : Set your desired equity risk limit per trade, up to 10%.
- **Maximum allowed spread pips** : 60 by default (0.60\$ in gold price).
- Verify your **EA Magic Number** (Default: 9999). If executing multiple independent algorithms on this account, assign a unique identifier to AlphaBox Cloud to ensure isolated trade management.
- Click **OK** .



5. OPERATIONAL VERIFICATION

Confirm the system is actively receiving telemetry from the cloud.

- Verify the **Algo Trading** toggle in the MetaTrader toolbar is activated (GREEN).
- Verify the AlphaBox HUD on your chart displays: **Connection: ONLINE**.
- Open the **Experts** tab located in the bottom Toolbox panel.
- Confirm the arrival of the following authentication receipt:


✅ CONNECTION ONLINE: Terminal successfully authenticated to AlphaBox Main Cloud.

YOUR TERMINAL IS NOW SECURELY INTEGRATED WITH THE ALPHABOX CLOUD
EXECUTION ENVIRONMENT.

THANK YOU FOR YOUR TIME AND WELCOME TO ALPHABOX.

INSTITUTIONAL EXECUTION INFRASTRUCTURE

INFRASTRUCTURE POWERED BY



Regulatory & Execution Disclaimer: AlphaBox EA operates strictly as a proprietary algorithm developer and non-custodial technology provider (B2B/ISV). We are not a broker-dealer, we do not provide financial advice, and we do not accept direct client deposits. All capital custody, regulatory compliance, and execution routing are managed exclusively by the client's chosen regulated brokerage entity. Performance metrics and historical track records are based on verified trade executions. Past performance is not indicative of future results. AlphaBox software and services are not intended for distribution to, or use by, any person in any jurisdiction where such distribution or use would be contrary to local law or regulation.

For integration assistance & technical support, please contact Deployment Team:

support@alphaboxea.com

